

Patons

PRICE
CODE C 1455
46-51 cm
18-20 in

FAIRYTALE DK



CHOICE OF TEXTURE . . .

bobble or loopy jackets with matching hats . . .
pull-ups and mitts complete these cosy outfits

Jackets

To fit chest

46	51	cm
18	20	in

Finished length, approx

24	29	cm
9½	11½	in

Sleeve seam, approx

14	17	cm
5½	6½	in

Patons Beehive Double Knitting

Bobble Jacket

3	3	50 gram balls
---	---	---------------

Loopy Jacket

4	5	50 gram balls
---	---	---------------

Patons Fairytale DK

Bobble Jacket

3	3	50 gram balls
---	---	---------------

Loopy Jacket

4	5	50 gram balls
---	---	---------------

Hats

Patons Beehive DK

Bobble Hat

2	2	50 gram balls
---	---	---------------

Loopy Hat

2	2	50 gram balls
---	---	---------------

Patons Fairytale DK

Bobble Hat

2	2	50 gram balls
---	---	---------------

Loopy Hat

2	2	50 gram balls
---	---	---------------

Pull-ups

Front seam

20	23	cm
8	9	in

Patons Beehive DK

2	3	50 gram balls
---	---	---------------

Patons Fairytale DK

3	3	50 gram balls
---	---	---------------

Mitts

Patons Beehive DK

1	1	50 gram ball
---	---	--------------

Patons Fairytale DK

1	1	50 gram ball
---	---	--------------

Keep ball bands for washing and pressing instructions.

Caution

It is essential to work to the stated tension, and Patons and Baldwins Limited cannot accept responsibility for the finished product if any yarn other than the recommended Patons yarns is used.

Buy the full amount of yarn at one time to avoid variations in dyelots.

Pair each Nos 3¼ mm and 4 mm Milward needles. Needle sizes quoted are Metric: equivalent UK sizes are No 10 for 3¼ mm and No 8 for 4 mm.

7 [8] buttons for each Jacket. Elastic for Pull-ups and Mitts. 1 button for each Hat.

Check your tension

Cast on 11 sts on No 4 mm needles.

Work 15 rows in stocking stitch. Cast off. The square should measure 2 in each way.

Abbreviations

K=knit; P=purl; st=stitch; yfwd=yarn forward; yrn=yarn round needle; tog=together; tbi=through back of loops.

inc=increase by working into front and back of stitch; dec=decrease by working 2 stitches together.

beg=beginning; alt=alternate; rep=repeat; patt=pattern; in=inches; cm=centimetres; mm=millimetres.

M1=make 1 stitch by picking up horizontal loop lying before next stitch and working into back of it.

ML=make loop by inserting needle into next stitch and winding yarn over point of needle and 1st finger of left hand 3 times, then over needle again, draw 4 loops through stitch, place loops back on left needle and K the 4 loops and stitch together through back of loops.

MB=make bobble as follows: (K1, P1) 3 times, K1 into next st, then pass 2nd, 3rd, 4th, 5th, 6th and 7th sts over first st.

Bobble Jacket

BACK

With No 3¼ mm needles, cast on 49 [57] sts and work in K1, P1 rib for 1 in, rows on right side having a K1 at each end, ending with **wrong** side facing for next row.

Change to No 4 mm needles and work in **bobble patt** as follows:

1st row—P. **2nd row**—K2, MB, * K3, MB; rep from * to last 2 sts, K2. **3rd and 5th rows**—P.

4th row—K. **6th row**—K4, MB, * K3, MB; rep from * to last 4 sts, K4. **7th row**—P. **8th row**—K.

These 8 rows form bobble patt.

Continue straight in patt until Back measures approx 5 [6] in, ending with a 3rd or 7th patt row.

Keeping continuity of patt, **** shape raglans** by casting off 2 sts at beg of next 2 rows. Work 2 rows.

Dec 1 st at each end of next and following 4th row. Work 3 [1] rows.

Now dec 1 st at each end of next and every following alt row until 17 [19] sts remain. Work 1 row.

Leave remaining sts on a length of yarn.

LEFT FRONT

With No 3¼ mm needles, cast on 25 [29] sts and work as for Back until Front measures 5 [6] in, ending with same patt row as on Back.

Keeping continuity of patt, **** shape raglan** by casting off 2 sts at beg of next row. Work 3 rows.

Now dec 1 st at beg of next and following 4th row. Work 3 [1] rows.

Dec 1 st at beg of next and every following alt row until 13 [15] sts remain. Work 1 row.

Shape neck as follows: **Next row**—Work 2tog, patt 8 [9], turn and leave remaining sts on a safety-pin.

Dec 1 st at neck edge on next and every row, **at the same time** dec 1 st at raglan edge as before on every following alt row until 3 [4] sts remain.

Dec 1 st at raglan edge **only** on following 1 [2] alt rows.

Next row—P2. **Next row**—K2tog and fasten off.

RIGHT FRONT

Work as for Left Front, reversing shapings.

SLEEVES

**** With No 3¼ mm needles**, cast on 27 [29] sts and work in K1, P1 rib for 1 in, rows on right side having a K1 at each end, ending with right side facing for next row.

Next row—(Rib 3, M1) 3 [2] times, (rib 2, M1) 4 [8] times, (rib 3, M1) 3 [2] times, rib 1 (37 [41] sts). ******

Change to No 4 mm needles and work in bobble patt as on Back until Sleeve measures approx 5½ [6½] in measured down centre, ending with a 3rd or 7th row of patt.

Keeping continuity of patt, ***** shape raglans** by casting off 2 sts at beg of next 2 rows. Work 2 rows.

Dec 1 st at each end of next and following 4th row.

Work 3 rows, then dec 1 st at each end of next and every following alt row until 5 sts remain, ending with right side facing.

Leave sts on a length of yarn.

MAKE UP AND BORDERS

Do not press.

**** Using flat seam** for ribbing and a fine back-stitch for remainder, join raglan, side and sleeve seams.

Neck Border: With right side facing and No 3¼ mm needles, K3 [4] sts from right front, **knit up** 6 [8] sts up right side of neck, K5 from sleeve, 17 [19] from back of neck, 5 from sleeve, **knit up** 6 [8] sts down left side of neck, K3 [4] from left front (45 [53] sts).

Work 7 rows P1, K1 rib, rows on **wrong** side having a P1 at each end.

Cast off evenly in rib.

Button Border: With No 3¼ mm needles, cast on 7 sts.

1st row—(Right side), K2, (P1, K1) twice, K1. **2nd row**—K1, (P1, K1) 3 times.

Rep these 2 rows until strip, when slightly stretched, fits up Left Front to top of Neck Border.

Sew in position as you go along.

Cast off evenly in rib.

Buttonhole Border: Work as for Button Border to fit up Right Front, with the addition of 7 [8] buttonholes, first to come ½ in above lower edge, last to come level with centre of Neck Border and remainder spaced evenly between. First mark position of buttons on Button Border with pins to ensure even spacing, then work buttonholes to correspond.

To make a buttonhole—(Right side), rib 3, yrn, P2tog, rib to end.

Sew on buttons.

Bobble Hat

With No 3¼ mm needles, cast on 87 [95] sts.

1st row—(Right side), K2, * P1, K1; rep from * to last st, K1. **2nd row**—K1, * P1, K1; rep from * to end. Rep these 2 rows once.

Next row—Rib 3, yrn, P2tog, rib to end. Work 3 rows more in rib.

Next row—Cast off 11 sts in rib, rib to last 11 sts, cast off 11 sts in rib (65 [73] sts).

Change to No 4 mm needles and with **wrong** side facing, rejoin yarn to remaining sts and work in patt as for Back of Jacket until Hat measures 5 in, ending with right side facing for next row.

Next row—Cast off 22 [24] sts, patt 21 [25] (including st on needle after cast off), cast off 22 [24].

With **wrong** side facing, rejoin yarn to remaining sts and continue in patt until Hat measures 4 [4½] in from cast-off sts, ending with a 3rd or 7th patt row.

Cast off.

MAKE UP AND LOWER BORDER

Do not press.

** Sew side edges of centre to cast-off sts.

With No 3¼ mm needles and right side facing, **knit up** 67 [75] sts along lower edge of Hat.

Work 7 rows in rib as for start of Hat, starting with a 2nd row.

Cast off evenly in rib.

Sew sides of Border along cast-off edges of ribbing at start of Hat, leaving 6 sts free at each side.

Sew on button.

Loopy Jacket

BACK

With No 3¼ mm needles, cast on 49 [57] sts and work in K1, P1 rib for 1 in, rows on right side having K1 at each end, ending with **wrong** side facing for next row.

Change to No 4 mm needles and work in **loopy patt** as follows:

1st row—P. **2nd row**—K. **3rd row**—K1, * ML, K1; rep from * to end.

4th and 6th rows—K. **5th row**—P. **7th row**—K2, ML, * K1, ML; rep from * to last 2 st, K2. **8th row**—K.

These 8 rows form patt.

Continue in loopy patt until Back measures 5 [6] in, ending with right side facing for next row.

Keeping continuity of loopy patt, work as for Back of Bobble Jacket from ** to end.

LEFT FRONT

With No 3¼ mm needles, cast on 25 [29] sts and work in K1, P1 rib for 1 in, rows on right side having a K1 at each end, ending with **wrong** side facing for next row.

Change to No 4 mm needles and work in loopy patt until Front matches Back at side edge, ending with right side facing for next row.

Keeping continuity of loopy patt, work as for Left Front of Bobble Jacket from ** to end.

RIGHT FRONT

Work as for Left Front, reversing shapings.

SLEEVES

Work as for Sleeves of Bobble Jacket from ** to **.

Change to No 4 mm needles and work in loopy patt as on Back until Sleeve measures 5½ [6½] in measured down centre, ending with right side facing for next row.

Keeping continuity of loopy patt, work as for Sleeves of Bobble Jacket from *** to end.

MAKE UP AND BORDERS

Do not press.

Work as for make up of Bobble Jacket from ** to end.

Loopy Hat

Work as for Bobble Hat, working **loopy patt** in place of bobble patt and ending with right side facing in place of a 3rd or 7th patt row before cast off.

TO MAKE UP

Do not press. Work as for Bobble Hat from ** to end.

Pull-ups

RIGHT LEG

With No 3¼ mm needles, cast on 62 [66] sts and work in K1, P1 rib for 1 in.

Change to No 4 mm needles and work as follows:

1st row—K. **2nd row**—P.

Shape back as follows: ** **1st row**—K12 [14], turn. **2nd and every alt row**—P. **3rd row**—K18 [20], turn. **5th row**—K24 [26], turn.

Continue thus, working 6 sts more on every K row until the row "K42 [44], turn" has been worked. **Next row**—P to end.**

*** Continue in stocking stitch across all sts inc 1 st at each end of 5th [7th] and every following 10th row until there are 72 [76] sts.

Work a few rows straight until Front seam (short edge of work) measures 8 [9] in, ending with a P row.

Place a marker at each end of last row.

Shape leg as follows: **1st row**—K1, K2togtbl, K to last 3 sts, K2tog, K1.

2nd row—P1, P2tog, P to last 3 sts, P2togtbl, P1.

Rep last 2 rows twice more (60 [64] sts).

Now dec 1 st as before at each end of next and every following 3rd row until 34 [36] sts remain.

Work straight until Leg measures 7 [8] in from markers (measured down centre), ending with a P row.***

Divide for foot as follows: **Next row**—K to last 6 sts, turn and leave these 6 sts on a safety-pin.

Next row—P to last 15 [16] sts, turn and leave these 15 [16] sts on a safety-pin.

**** Work 10 [12] rows stocking stitch on remaining 13 [14] sts.

Dec 1 st at each end of next and following alt row (9 [10] sts).

Next row—P. Break yarn.****

With right side facing, rejoin yarn to inside edge of 15 [16] sts left and **knit up** 8 [9] sts along side of foot, K across 9 [10] sts on needle, **knit up** 8 [9] sts along other side of foot, then K 6 sts from safety-pin.

Next row—K to end, then K15 [16] sts from safety-pin (46 [50] sts).

K 6 [8] rows.

Shape foot as follows: **1st row**—K2 [3], K2tog, K2 [1], K2tog, K17 [19], K2tog, K1 [2], K2tog, K16 [17]. **2nd row**—K.

3rd row—K1 [2], K2tog, K2 [1], K2tog, K15 [17], K2tog, K1 [2], K2tog, K15 [16]. **4th row**—K.

Cast off.

LEFT LEG

With No 3¼ mm needles, cast on 62 [66] sts and work in K1, P1 rib for 1 in.

Change to No 4 mm needles and work as follows: **Next row**—K.

Shape back as follows: Work as for Right Leg from ** to **, reading "P" for K and "K" for P.

Next row—P.

Work as for Right Leg from *** to ***.

Divide for foot as follows: **Next row**—K to last 15 [16] sts, turn and leave these 15 [16] sts on a safety-pin.

Next row—P to last 6 sts, turn and leave these 6 sts on a safety-pin.

Work as for Right Leg from **** to ****.

With right side facing, rejoin yarn to inside edge of 6 sts left and **knit up** 8 [9] sts along side of foot, K across 9 [10] sts on needle, **knit up** 8 [9] sts along other side of foot, K15 [16] sts from safety-pin.

Next row—K to end, then K across 6 sts from safety-pin (46 [50] sts).

K 6 [8] rows.

Shape foot as follows: **1st row**—K16 [17], K2tog, K1 [2], K2tog, K17 [19], K2tog, K2 [1], K2tog, K2 [3]. **2nd row**—K.

3rd row—K15 [16], K2tog, K1 [2], K2tog, K15 [17], K2tog, K2 [1], K2tog, K1 [2]. **4th row**—K.

Cast off.

TO MAKE UP

Do not press.

Using a flat seam for ribbing and garter stitch and a fine back-stitch seam for remainder, join front and back seams to markers, then join leg and foot seams.

Cut elastic to fit waist and sew inside waist ribbing, using a herringbone stitch over elastic to form a casing.

Mitts

With No 3¼ mm needles, cast on 29 [33]

sts and work in K1, P1 for 1½ in, rows on right side having a K1 at each end.

Next row—K1, * yfwd, K2tog; rep from * to end. **Next row**—P, dec 1 st at centre (28 [32] sts).

Change to No 4 mm needles and starting with a K row, work in stocking stitch until Mitt measures 4 [4½] in, ending with right side facing for next row.

Shape top as follows: **1st row**—(K1, K2togtbl, K8 [10], K2tog, K1) twice. **2nd and 4th rows**—P.

3rd row—(K1, K2togtbl, K6 [8], K2tog, K1)

twice. **5th row**—(K1, K2togtbl, K4 [6], K2tog, K1) twice.

6th row—P.

Cast off.

TO MAKE UP

Do not press.

Using a flat seam for ribbing and a fine back-stitch seam for remainder, join seam.

Cut length of elastic to fit wrist, thread through holes at wrist and join ends.

WASHING AND CARING FOR PATONS YARNS

Hand washing is always best. For yarns made mainly of wool use warm water, a warm rinse, squeeze out between towels or spin-dry (normal cycle), then dry flat after easing into shape. Do not dry in direct heat (radiators or fires). Do not dry white handknits in direct sunlight. For yarns made mainly of acrylics it is important that you rinse in cold water and if you spin-dry use the short cycle.

A great many people now use washing machines. The ball band will show whether the yarn you have chosen is suitable for machine-washing: if it is, follow these four "golden rules".

1. Make sure the garment is knitted correctly according to the Patons pattern, on the correct needles to the correct tension.
2. Don't have the water hotter than the recommended temperature.
3. Use the machine on a gentle cycle.
4. Don't leave the garment in the machine too long.

The wrappers on all Patons yarns show the appropriate International Textile Care Labelling Code symbols for the yarn. Examples are shown here. The latest automatic machines have these International Care Symbols, and provided your machine is not connected to the domestic hot water supply (when you need to be careful about the heat) all you have to

do is match the programme to our symbols. Older types of machine will not have these controls and it may be more difficult to ensure the correct combination of temperature, agitation and time.

If you are in any way unsure about the application of the symbols to your machine it is safest to hand-wash.

WASH SYMBOLS

	Machine	Hand wash
	Warm (40°C)	Warm (40°C)
	Maximum wash	
	Normal rinse and spin	
	Warm (40°C)	Warm (40°C)
	Minimum wash	
	Cold rinse	Short spin
	Machine	Hand wash
	Warm (40°C)	Warm (40°C)
	Minimum wash	Do not rub
	Spin	Do not rub or hand-wring
	Dry flat	

Hand wash only		
	Warm (40°C)	
	Warm rinse	Do not rub or hand-wring
	Dry flat	
BLEACH SYMBOLS		Household bleach can be used
		Do not bleach
IRONING SYMBOLS		Cool Iron (120°C)
		Warm Iron (160°C)
		Do not Iron
DRY CLEANING SYMBOLS	(A)	Dry cleanable in all solvents
	(F)	Dry cleanable in certain solvents
	(P)	Consult cleaner
		Do not dry clean

We shall be happy to deal with your queries if you write to Sarah Bell, Patons & Baldwins Limited, Alloa, Scotland, enclosing a ball band of the yarn specified and a stamped addressed envelope.

PUBLISHED BY PATONS & BALDWIN'S LIMITED

WARNING - COPYRIGHT All Patons patterns are protected by the law of copyright and may not be reproduced either by photocopying or any other means. They are sold on condition that they are used only for non-commercial purposes. All other rights are expressly reserved by Patons & Baldwins Limited to whom applications for commercial licences should be addressed.